

# Používanie SMTP servera

Pre odosielanie mailov s  
EVP, VF, .....

# Odosielanie mailov

(Technická informácia)

Táto zmena sa týka iba tých používateľov, ktorí na rozosielanie faktúr používajú mailový server **mail.compeko.sk** alebo **smtp.compeko.sk**.

Prevádzkovateľ domény compeko.sk zmenil nastavenia bezpečnosti mailovej komunikácie tak, že odosielateľ musí byť zhodný s mailovou schránkou, cez ktorú sa mail odosiela.

Dôsledkom je, že pri používaní uvedených mailových serverov už musí byť ako odosielateľ uvedený **mailer@compeko.sk** a smtp server **smtp.webglobe.sk**. Program v tomto prípade upraví text mailu tak, že pôvodne uvedená spätná adresa sa u prijímateľa nezobrazí ako adresa odosielateľa, ale bude iba v texte mailu. Ako odosielateľ bude vždy **mailer@compeko.sk**.

# Odosielanie mailov

Parametre: W:\MZD\DATA999\MZPARW.DBF

Zoznam | Parameter | -1

Význam parametra	Typ	Dĺžka	Hodnota	Parameter	Uprava
MAIL: SMTP server pre mailing	C	0	mail.compeko.sk	EVP_SMTPS	
MAIL: SMTP užívateľ	C	0	mailer@compeko.sk	EVP_SMTPU	
MAIL: SMTP heslo	C	0	jnEAZdf3	EVP_SMTPP	
MAIL: požaduje sa TLS	C	1	A	EVP_SMTPT	
MAIL: požaduje sa FQDN	C	0		EVP_SMTPDN	
MAIL: požaduje sa potvrdenie	C	1	N		
MAIL: odosielateľ	C	0	dekanek@firma.sk		
MAIL: meno	C	0	Vanda Testovacia		
EVP: funkcia	C	0	mzdova účtovníčka		

Parametre: W:\MZD\DATA999\MZPARW.DBF

Zoznam | Parameter | 128

Parameter: EVP\_SMTPS | MAIL: SMTP server pre mailing

Pre automatické rozosielanie niektorých údajov mailom (e-pásy, DDS, TREXIMA, ...) je potrebné určiť meno mailového SMTP servera, ktorý sa pre rozosielanie má použiť. Ak sa pre odosielanie má použiť neštandardný port, je možné ho zapísať za názov SMTP servera s oddeľovačom ":" (napr. mail.firma.sk:582)

Štandardná hodnota: mail.compeko.sk

Hodnota: smtp.webglobe.sk

Posledná aktualizácia: 19.01.2022 : Test Test (TT)

Zápis | Návrat

Odosielateľa zmeniť  
netreba, úpravu  
vykoná program

Toto je povinná  
zmena

# Odosielanie mailov


*Iné riešenie zdarma:*

Vytvorte si vlastné konto pre rozosielanie mailov na portáli [sendinblue.com](https://www.sendinblue.com).  
Krátky návod ako na to, je tu:

- Treba sa prihlásiť do <https://www.sendinblue.com>
- Treba si tam vytvoriť vlastné konto:
  - - vpravo hore je Sign up free, na to treba kliknúť
  - - treba uviesť existujúcu mailovú adresu, lebo na ňu príde potvrdzovací mail
  - - potom sa treba s novovytvoreným kontom prihlásiť
- a potom:

# Odosielanie mailov

- Klik vpravo hore na rozbalovaciu sipku
- Potom klik na SMTP & API



The screenshot shows the Sendinblue dashboard interface. The top navigation bar includes 'Campaigns', 'Automation', 'Transactional', and 'Contacts'. The user's name 'Backup s.r.o.' is visible in the top right corner, circled in red. A dropdown menu is open, showing the user's email 'melkner.peter@gmail.com', 'My plan', 'Plugins', 'Senders & IP', 'SMTP & API' (circled in red), 'Users', 'Support & tickets', 'Security', 'Select your language', and 'Logout'. The main dashboard area displays three metrics: 'All your contacts' (1), 'opened' (0, 0%), and 'clicked' (0, 0%). Below these is an 'Email Campaigns' section with the message 'No campaign found' and a '+ Create a New Campaign' button. The left sidebar contains navigation options: Dashboard, Email, Templates, Statistics, and Settings. The bottom left corner shows account details: 'Plan FREE', '299 emails Remaining for today', 'Upgrade', '0 SMS Credits', 'Expire : Never', and 'Get more credits'.

# Odosielanie mailov

Potom klik na SMTP

The screenshot shows the 'SMTP & API' settings page in the Sendinblue dashboard. The top navigation bar includes 'Campaigns', 'Automation', 'Transactional', and 'Contacts'. The left sidebar lists various settings like 'My Plan', 'My Profile', 'Senders & IPa', 'Plugins', 'SMTP & API', 'Support', 'Settings', 'Users', and 'Security'. The main content area is titled 'SMTP & API' and features a blue button 'UPDATE A NEW SMTP KEY'. Below this, there are two tabs: 'API Keys' and 'SMTP'. The 'SMTP' tab is active, showing 'Your SMTP settings' with the following details: SMTP SERVER: smtp-relay.sendinblue.com, PORT: 587, and LOGIN: MAILER@SENDINBLUE.COM. Below the settings is a section for 'YOUR SMTP keys' with a table containing columns for SMTP KEY NAME, SMTP KEY VALUE, and CREATED. The 'Master password' row shows a key name and a value that has been redacted with a black box.

SMTP KEY NAME	SMTP KEY VALUE	CREATED
Master password	[REDACTED]	

# Odosielanie mailov

Z tohto okna si treba zapamätať tieto údaje:

The screenshot shows the 'SMTP & API' settings page. The 'SMTP' tab is selected. Under 'Your SMTP settings', the following fields are highlighted with red circles: SMTP Server (smtp-relay.sendinblue.com), Port (587), and Login (mailer@compeko.sk). Under 'Your SMTP keys', a table lists the 'Master password' with a value starting with 'rG' followed by a blacked-out area, also highlighted with a red circle.

## SMTP & API

API Keys **SMTP**

### Your SMTP settings

SMTP Server: smtp-relay.sendinblue.com

Port: 587

Login: mailer@compeko.sk

### Your SMTP keys

SMTP KEY NAME	SMTP KEY VALUE
Master password	rG [REDACTED]

# Odosielanie mailov

A tie potom zapísať do parametrov príslušného podsystému

Typ zhlavíia programu	C	U		CAPTTYPE
<b>EVF: SMTP server pre mailing</b>	C	0	smtp-relay.sendinblue.com:587	<b>EVF_SMTPS</b>
<b>EVF: SMTP užívateľ</b>	C	0	mailer@compeko.sk	<b>EVF_SMTPU</b>
<b>EVF: SMTP heslo</b>	C	0	rGU [REDACTED]	<b>EVF_SMTPP</b>
<b>EVF: požaduje sa TLS</b>	C	1	N	<b>EVF_SMTPT</b>
<b>EVF: odosielať</b>	C	0	test@faktury.sk	<b>EVF_from</b>
<b>EVF: ...</b>	C	10	710	<b>EVF_CT</b>



